

Natural Nucleus Error Messages

NAT7501-NAT7550

NAT7508: Compression table full.

Text	Compression table full.
Actn.	Increase value of CMPRTSZ parameter in Natural parameter module.

NAT7509: GETMAIN failed for Entire.

Text	GETMAIN failed for Entire.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7510: GETMAIN failed for CON-NECT.

Text	GETMAIN failed for CON-NECT.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7511: GETMAIN failed for TRS.

Text	GETMAIN failed for TRS.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7512: GETMAIN failed for VSAM.

Text	GETMAIN failed for VSAM.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7513: GETMAIN failed for EDITOR.

Text	GETMAIN failed for EDITOR.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7514: GETMAIN failed for PROCESS (ASIZE).

Text	GETMAIN failed for PROCESS (ASIZE).
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment: Increase your region size or increase the size of your Natural thread when running in a thread environment.

NAT7515: GETMAIN failed for DEBUG.

Text	GETMAIN failed for DEBUG.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7516: GETMAIN failed for PC-CONNECTION.

Text	GETMAIN failed for PC-CONNECTION.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

NAT7540: GETMAIN failed for DB2.

Text	GETMAIN failed for DB2.
------	-------------------------

NAT7543: GETMAIN failed for USERBUF buffer.

Text	GETMAIN failed for USERBUF buffer.
------	------------------------------------

NAT7544: Getmain failed for :1:.

Text	Getmain failed for :1:.
------	-------------------------

NAT7545: GETMAIN of :1: for :2: buffer failed (:3:/:4:).

Text	GETMAIN of ... for ... buffer failed (Reason/Response).
Expl.	The requested buffer size exceeded the available space in the current thread/partition/region/task. For details see reason code and response code from operating system.
Actn.	Either decrease the size of the buffer, or start Natural in a larger thread/partition/region/task.

NAT7547: GETMAIN failed for :1: buffer - :2: unavailable.

Text	GETMAIN failed for ... buffer - :2: unavailable.
Expl.	The aquisition of an optional buffer has failed. The component using this buffer will be not available.
Actn.	Increase the thread/region size or decrease other buffer sizes to get more storage available. Then restart the Natural session.